Installing FA-124 in the XP SP2 Compatibility Mode

Important!

Be sure to install FA-124 before connecting the calculator to your computer.

1) Place the CD-ROM in your computer's CD-ROM drive.

If the screen shown below appears, click the item shown circled in red below.

	🖬 AutoPlay 💼 📼 💌
	CD Drive (D:) fx-9860G
	Always do this for software and games:
	Install or run program
	Run fx9860G.exe Publisher not specified
	General options
\langle	Open folder to view files using Windows Explorer
	Set AutoPlay defaults in Control Panel

If the screen shown above does not appear, select "Computer" on the Windows Start menu.



Next, navigate to the drive that shows a calculator icon, right-click the icon, and then select "Open" on the shortcut menu that appears.



2) On the screen that appears, open the folder named "FA124".

Comput	Q							
🐚 Organize 👻 🏢 Views 👻 🕐								
Favorite Links	Name	Date modified	Туре	Size				
Documents	퉬 Add-in_Apl	12/25/2006 9:04 PM	File Folder					
Distance	퉲 Apl_Guide	12/25/2006 8:55 PM	File Folder					
Pictures	Bin	12/25/2006 7:30 PM	File Folder					
🕼 Music	퉲 FA124 🔪	12/25/2006 8:37 PM	File Folder					
🕼 Recently Changed	keader	12/26/2006 2:31 PM	File Folder					
🛛 🖗 Searches	퉬 UsersGuide	12/25/2006 8:14 PM	File Folder					
Public	📰 autorun	7/19/2006 9:44 AM	Setup Information	1 KB				
	▶ fx9860G	10/21/2004 5:38 PM	Application	124 KB				
	📓 fx9860G	7/18/2006 7:57 PM	Icon	2 KB				
	🗊 fx9860G	12/27/2006 9:22 AM	Configuration Sett	1 KB				
			_					

3) Open the "FA124_inst" folder.



4) Right-click the "Setup" file (shown circled in red below). On the shortcut menu that appears, select "Properties".

C CD Drive (D:) fx-9860G → FA124 → FA124_inst → - 47 Search P									
Image: Organize ▼ III Views ▼ Image: Open (2)									
Favorite Links	Name	Date modified	Туре	Size					
 Documents Pictures Music Recently Changed Searches Public 	data1 data1.hdr data2 ikernel.ex_ loyout.hin Set Set Set Copy Create Shortco Properties	5/10/2005 1:14 PM 5/10/2005 1:14 PM 5/10/2005 1:14 PM 7/26/2002 9:07 AM 5/10/2005 1:14 PM 0.5/2001 2:22 AM PM strator PM	Cabinet File HDR File Cabinet File EX_File BIN File Application Configuration Sett INX File	500 KB 18 KB 1,781 KB 339 KB 1 KB 55 KB 1 KB 132 KB					

5) On the Setup Properties dialog box that appears, select the "Compatibility" tab. Under "Compatibility mode", select the check box next to "Run this program in compatibility mode for". Next, click the right arrow button and select "Windows XP (Service Pack 2)". Finally, click [OK].

Setup Properties						
General Compatibility Security Details						
If you have problems with this program and it worked correctly on an earlier version of Windows, select the compatibility mode that matches that earlier version.						
Compatibility mode						
Bun this program in compatibility mode for:						
Windows XP (Service Pack 2)						
Settings						
Run in 256 colors						
Run in 640 x 480 screen resolution						
Disable visual themes						
Disable desktop composition						
Disable display scaling on high DPI settings						
Privilege Level						
Run this program as an administrator						
Show settings for all users						
OK Cancel Apply						

- 6) On the screen shown in step 4) above, start up the "Setup" application (circled in red, above).
- 7) If the User Account Control screen appears, select the "Allow" item to proceed.

8) Starting with the next screen that appears, follow the instructions that appear on the installer screens to install FA-124.



Installation Precautions

The first time you connect the calculator to your computer after installing FA-124, the calculator will search for the calculator USB driver. When this happens, perform the following steps.

1) If the screen shown below appears, select the item shown circled in red below.



2) If the User Account Control screen appears, select the "Allow" item to proceed with driver software installation.

3) When the warning message shown below appears, select the item shown circled in red below to proceed with installation.



4) Calculator USB driver installation is complete when the message shown below appears in the Windows taskbar.

